２０２２年１２月（２階フロア）の

コンディションは、４１ｆｅｅｔです。

Brunswick PBA Official Lane Maintenance and Capital Equipment Provider

DIRECT+ Conditioning System

X ENVOY

AUTHORITY22

Select Machine

Pattern Information

Date	2022 12/1
Pattern Type	Recreational
Pattern Difficulty	Medium
Pattern Designer	ALee
Pattern Volume (ml)	23.20

Surface Information

Surface Type	Synthetic
Surface Brand	
Age	6

Pattern Parameters

Pattern Number	1
Pattern Name	2022 12 所沢
Mode	Clean & Oil
Forward Speed	Max Clean
Start Cleaner Spray	0
Start Squeegee	0
Start Oiling	6
Split Pattern	No

Supplies Information

Lane Cleaner	Brunswick MAX 10	
Cleaner Mixture Ratio	10 : 1	
Cleaner Transition Distance		Authority22
Cleaner Spray End Distance	45	Envoy
Lane Conditioner	Bruswick Logic	

Notes 今月のレーンコンディションは 41F です。
オイル量等の数値は先月と変わりませんが、マシンの
出力調整をしたため先月よりオイルを感じるかもしれません。

Zone	1	2	3	4	5	6	7	8
Zone End Distance	15	20	25	30	36	41	0	0
Zone Ratio L	4.5 : 1	5.0 : 1	6.3 : 1	8.0 : 1	1.0 : 1	### : 1	### : 1	### : 1
Zone Ratio R	4.5 : 1	5.0 : 1	6.3 : 1	8.0 : 1	1.0 : 1	### : 1	### : 1	### : 1
Zone Volume (ml)	14.40	3.98	2.90	1.91	0.00	0.00	0.00	0.00

Board Number — 7 Pin Side

ZONE	L1	L2	L3	L4	L5	L6	L7	L8	L9	L10	L11	L12	L13	L14	L15	L16	L17	L18	L19	C20
1	10	10	10	10	15	25	40	50	60	70	80	90	90	90	90	90	90	90	90	90
2	7	7	7	7	10	20	30	45	55	60	65	75	75	75	75	75	75	75	75	75
3	5	5	5	5	7	10	20	25	30	40	45	50	55	60	60	60	60	60	60	60
4	3	3	3	3	5	7	10	15	15	20	25	30	35	40	40	45	45	45	45	45
5	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1
6	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0
7																				
8																				

Board Number — 10 Pin Side

ZONE	R19	R18	R17	R16	R15	R14	R13	R12	R11	R10	R9	R8	R7	R6	R5	R4	R3	R2	R1
1	90	90	90	90	90	90	90	90	80	70	60	50	40	25	15	10	10	10	10
2	75	75	75	75	75	75	75	75	65	60	55	45	30	20	10	7	7	7	7
3	60	60	60	60	60	60	55	50	45	40	30	25	20	10	7	5	5	5	5
4	45	45	45	45	40	40	35	30	25	20	15	15	10	7	5	3	3	3	3
5	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1
6	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0
7																			
8																			



2022 12 所沢

Conditioner:
Cleaner:

Zone Configuration



Cleaner Transition



Mode: Clean and Condition
Speed: Max Clean
Start Cleaner Spray: 0 Feet
Start Squeegee: 0 Feet
Start Conditioning: 6 Inches
Split Pattern: No

Zone 1	Avg	Ratio	Zone 2	Avg	Ratio
Left	20.0	4.5 : 1	Left	14.8	5.1 : 1
Right	20.0	4.5 : 1	Right	14.8	5.1 : 1
Center	90.0		Center	75.0	

Zone 3	Avg	Ratio	Zone 4	Avg	Ratio
Left	9.4	6.4 : 1	Left	5.6	8.0 : 1
Right	9.4	6.4 : 1	Right	5.6	8.0 : 1
Center	60.0		Center	45.0	

Zone 5	Avg	Ratio	Zone 6	Avg	Ratio
Left	1.0	1.0 : 1	Left	0.0	1.0 : 1
Right	1.0	1.0 : 1	Right	0.0	1.0 : 1
Center	1.0		Center	0.0	



3L-7L:18L-18R	Ratio by Total Volume	18L-18R:7R-3R
5.01	1	5.01